

# CS307&CS356: Operating Systems

Dept. of Computer Science & Engineering Chentao Wu wuct@cs.sjtu.edu.cn








# Download lectures

- <u>ftp://public.sjtu.edu.cn</u>
- User: wuct
- Password: wuct123456

• http://www.cs.sjtu.edu.cn/~wuct/os/

# Chapter 12: I/O Systems





# Chapter 12: I/O Systems


- Overview
- I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- Transforming I/O Requests to Hardware Operations
- STREAMS
- Performance





#### **Objectives**

- Explore the structure of an operating system's I/O subsystem
- Discuss the principles and complexities of I/O hardware
- Explain the performance aspects of I/O hardware and software





#### **Overview**

- I/O management is a major component of operating system design and operation
  - Important aspect of computer operation
  - I/O devices vary greatly
  - Various methods to control them
  - Performance management
  - New types of devices frequent
- Ports, busses, device controllers connect to various devices
- Device drivers encapsulate device details
  - Present uniform device-access interface to I/O subsystem






- Incredible variety of I/O devices
  - Storage
  - Transmission
  - Human-interface
- Common concepts signals from I/O devices interface with computer
  - **Port** connection point for device
  - Bus daisy chain or shared direct access
    - PCI bus common in PCs and servers, PCI Express (PCIe)
    - expansion bus connects relatively slow devices
    - Serial-attached SCSI (SAS) common disk interface
  - **Controller** (host adapter) electronics that operate port, bus, device
    - Sometimes integrated
    - Sometimes separate circuit board (host adapter)
    - Contains processor, microcode, private memory, bus controller, etc.
      - Some talk to per-device controller with bus controller, microcode memory, etc




### **A Typical PC Bus Structure**





# I/O Hardware (Cont.)


- Fibre channel (FC) is complex controller, usually separate circuit board (host-bus adapter, HBA) plugging into bus
- I/O instructions control devices
- Devices usually have registers where device driver places commands, addresses, and data to write, or read data from registers after command execution
  - Data-in register, data-out register, status register, control register
  - Typically 1-4 bytes, or FIFO buffer
- Devices have addresses, used by
  - Direct I/O instructions
  - Memory-mapped I/O
    - Device data and command registers mapped to processor address space
    - Especially for large address spaces (graphics)





#### **Device I/O Port Locations on PCs (partial)**

I/O address range (hexadecimal)	device	
000–00F	DMA controller	
020–021	interrupt controller	
040–043	timer	
200–20F	game controller	
2F8-2FF	serial port (secondary)	
320–32F	32F hard-disk controller	
378–37F	parallel port	
3D0-3DF	graphics controller	
3F0–3F7	diskette-drive controller	
3F8–3FF	serial port (primary)	





# Polling

- For each byte of I/O
  - 1. Read busy bit from status register until 0
  - Host sets read or write bit and if write copies data into data-out register
  - 3. Host sets command-ready bit
  - 4. Controller sets busy bit, executes transfer
  - 5. Controller clears busy bit, error bit, command-ready bit when transfer done
- Step 1 is busy-wait cycle to wait for I/O from device
  - Reasonable if device is fast
  - But inefficient if device slow
  - CPU switches to other tasks?
    - But if miss a cycle data overwritten / lost






- Polling can happen in 3 instruction cycles
  - Read status, logical-and to extract status bit, branch if not zero
  - How to be more efficient if non-zero infrequently?
- CPU Interrupt-request line triggered by I/O device
  - Checked by processor after each instruction
- Interrupt handler receives interrupts
  - Maskable to ignore or delay some interrupts
- Interrupt vector to dispatch interrupt to correct handler
  - Context switch at start and end
  - Based on priority
  - Some nonmaskable
  - Interrupt chaining if more than one device at same interrupt number



# **Interrupt-Driven I/O Cycle**





## Interrupts (Cont.)

- Interrupt mechanism also used for exceptions
  - Terminate process, crash system due to hardware error
- Page fault executes when memory access error
- System call executes via trap to trigger kernel to execute request
- Multi-CPU systems can process interrupts concurrently
  - If operating system designed to handle it
- Used for time-sensitive processing, frequent, must be fast







- Stressing interrupt management because even single-user systems manage hundreds or interrupts per second and servers hundreds of thousands
- For example, a quiet macOS desktop generated 23,000 interrupts over 10 seconds

Fri Nov 25 13:55:59			0:00:10
	SCHEDULER	INTERRUPTS	
total_samples	13	22998	
delays < 10 usecs	12	16243	
delays < 20 usecs	1	5312	
delays < 30 usecs	0	473	
delays < 40 usecs	0	590	
delays < 50 usecs	0	61	
delays < 60 usecs	0	317	
delays < 70 usecs	0	2	
delays < 80 usecs	0	0	
delays < 90 usecs	0	0	
delays < 100 usecs	0	0	
total < 100 usecs	13	22998	





#### Intel Pentium Processor Event-Vector Table

vector number	description	
0	divide error	
1	debug exception	
2	null interrupt	
3	breakpoint	
4	INTO-detected overflow	
5	bound range exception	
6	invalid opcode	
7	device not available	
8	double fault	
9	coprocessor segment overrun (reserved)	
10	invalid task state segment	
11	segment not present	
12	stack fault	
13	general protection	
14	page fault	
15	(Intel reserved, do not use)	
16	floating-point error	
17	alignment check	
18	machine check	
19–31	(Intel reserved, do not use)	
32–255	maskable interrupts	




# **Direct Memory Access**

- Used to avoid programmed I/O (one byte at a time) for large data movement
- Requires DMA controller
- Bypasses CPU to transfer data directly between I/O device and memory
- OS writes DMA command block into memory
  - Source and destination addresses
  - Read or write mode
  - Count of bytes
  - Writes location of command block to DMA controller
  - Bus mastering of DMA controller grabs bus from CPU
    - Cycle stealing from CPU but still much more efficient
  - When done, interrupts to signal completion
- Version that is aware of virtual addresses can be even more efficient
  DVMA




#### **Six Step Process to Perform DMA Transfer**





# **Application I/O Interface**

- I/O system calls encapsulate device behaviors in generic classes
- Device-driver layer hides differences among I/O controllers from kernel
- New devices talking already-implemented protocols need no extra work
- Each OS has its own I/O subsystem structures and device driver frameworks
- Devices vary in many dimensions
  - Character-stream or block
  - Sequential or random-access
  - Synchronous or asynchronous (or both)
  - Sharable or dedicated
  - Speed of operation
  - read-write, read only, or write only






#### **A Kernel I/O Structure**

kernel						
kernel I/O subsystem						
SAS device driver	keyboard device driver	mouse device driver		PCIe bus device driver	802.11 device driver	USB device driver
SAS device controller	keyboard device controller	mouse device controller		PCIe bus device controller	802.11 device controller	USB device controller
1	1	1	1	1	1	1
SAS devices	keyboard	mouse		PCIe bus	802.11 devices	USB devices (disks, tapes, drives)



### **Characteristics of I/O Devices**


aspect	aspect variation	
data-transfer mode	character block	terminal disk
access method	sequential random	modem CD-ROM
transfer schedule	synchronous asynchronous	tape keyboard
sharing	dedicated sharable	tape keyboard
device speed	latency seek time transfer rate delay between operations	
I/O direction	read only write only read-write	CD-ROM graphics controller disk



# Characteristics of I/O Devices (Cont.)


- Subtleties of devices handled by device drivers
- Broadly I/O devices can be grouped by the OS into
  - Block I/O
  - Character I/O (Stream)
  - Memory-mapped file access
  - Network sockets
- For direct manipulation of I/O device specific characteristics, usually an escape / back door
  - Unix ioctl() call to send arbitrary bits to a device control register and data to device data register
- UNIX and Linux use tuple of "major" and "minor" device numbers to identify type and instance of devices (here major 8 and minors 0-4) % ls -1 /dev/sda\*

brw-rw---- 1 root disk 8, 0 Mar 16 09:18 /dev/sda brw-rw---- 1 root disk 8, 1 Mar 16 09:18 /dev/sda1 brw-rw---- 1 root disk 8, 2 Mar 16 09:18 /dev/sda2 brw-rw---- 1 root disk 8, 3 Mar 16 09:18 /dev/sda3






- Block devices include disk drives
  - Commands include read, write, seek
  - Raw I/O, direct I/O, or file-system access
  - Memory-mapped file access possible
    - File mapped to virtual memory and clusters brought via demand paging
  - DMA
- Character devices include keyboards, mice, serial ports
  - Commands include get(), put()
  - Libraries layered on top allow line editing





#### **Network Devices**

- Varying enough from block and character to have own interface
- Linux, Unix, Windows and many others include socket interface
  - Separates network protocol from network operation
  - Includes select() functionality
- Approaches vary widely (pipes, FIFOs, streams, queues, mailboxes)





- Provide current time, elapsed time, timer
- Normal resolution about 1/60 second
- Some systems provide higher-resolution timers
- Programmable interval timer used for timings, periodic interrupts
- ioctl() (on UNIX) covers odd aspects of I/O such as clocks and timers







# Nonblocking and Asynchronous I/O


- **Blocking** process suspended until I/O completed
  - Easy to use and understand
  - Insufficient for some needs
- Nonblocking I/O call returns as much as available
  - User interface, data copy (buffered I/O)
  - Implemented via multi-threading
  - Returns quickly with count of bytes read or written
  - select() to find if data ready then read() or write() to transfer
- Asynchronous process runs while I/O executes
  - Difficult to use
  - I/O subsystem signals process when I/O completed





#### **Two I/O Methods**







- Vectored I/O allows one system call to perform multiple I/O operations
- For example, Unix readve() accepts a vector of multiple buffers to read into or write from
- This scatter-gather method better than multiple individual I/O calls
  - Decreases context switching and system call overhead
  - Some versions provide atomicity
    - Avoid for example worry about multiple threads changing data as reads / writes occurring






# **Kernel I/O Subsystem**

- Scheduling
  - Some I/O request ordering via per-device queue
  - Some OSs try fairness
  - Some implement Quality Of Service (i.e. IPQOS)
- Buffering store data in memory while transferring between devices
  - To cope with device speed mismatch
  - To cope with device transfer size mismatch
  - To maintain "copy semantics"
  - Double buffering two copies of the data
    - Kernel and user
    - Varying sizes
    - Full / being processed and not-full / being used
    - Copy-on-write can be used for efficiency in some cases




#### **Device-status Table**





#### **Common PC and Data-center I/O devices and Interface Speeds**





- Caching faster device holding copy of data
  - Always just a copy
  - Key to performance
  - Sometimes combined with buffering
- Spooling hold output for a device
  - If device can serve only one request at a time
  - i.e., Printing
- Device reservation provides exclusive access to a device
  - System calls for allocation and de-allocation
  - Watch out for deadlock





- OS can recover from disk read, device unavailable, transient write failures
  - Retry a read or write, for example
  - Some systems more advanced Solaris FMA, AIX
    - Track error frequencies, stop using device with increasing frequency of retry-able errors
- Most return an error number or code when I/O request fails
- System error logs hold problem reports






- User process may accidentally or purposefully attempt to disrupt normal operation via illegal I/O instructions
  - All I/O instructions defined to be privileged
  - I/O must be performed via system calls
    - Memory-mapped and I/O port memory locations must be protected too





### Use of a System Call to Perform I/O






#### **Kernel Data Structures**

- Kernel keeps state info for I/O components, including open file tables, network connections, character device state
- Many, many complex data structures to track buffers, memory allocation, "dirty" blocks
- Some use object-oriented methods and message passing to implement I/O
  - Windows uses message passing
    - Message with I/O information passed from user mode into kernel
    - Message modified as it flows through to device driver and back to process
    - Pros / cons?





### **UNIX I/O Kernel Structure**





- Not strictly domain of I/O, but much is I/O related
- Computers and devices use electricity, generate heat, frequently require cooling
- OSes can help manage and improve use
  - Cloud computing environments move virtual machines between servers
    - Can end up evacuating whole systems and shutting them down
  - Mobile computing has power management as first class OS aspect






## **Power Management (Cont.)**

- For example, Android implements
  - Component-level power management
    - Understands relationship between components
    - Build device tree representing physical device topology
    - System bus -> I/O subsystem -> {flash, USB storage}
    - Device driver tracks state of device, whether in use
    - Unused component turn it off
    - All devices in tree branch unused turn off branch
  - Wake locks like other locks but prevent sleep of device when lock is held
  - Power collapse put a device into very deep sleep
    - Marginal power use
    - Only awake enough to respond to external stimuli (button press, incoming call)
- Modern systems use advanced configuration and power interface (ACPI) firmware providing code that runs as routines called by kernel for device discovery, management, error and power management


# Kernel I/O Subsystem Summary

- In summary, the I/O subsystem coordinates an extensive collection of services that are available to applications and to other parts of the kernel
  - Management of the name space for files and devices
  - Access control to files and devices
  - Operation control (for example, a modem cannot seek())
  - File-system space allocation
  - Device allocation
  - Buffering, caching, and spooling
  - I/O scheduling
  - Device-status monitoring, error handling, and failure recovery
  - Device-driver configuration and initialization
  - Power management of I/O devices
- The upper levels of the I/O subsystem access devices via the uniform interface provided by the device drivers






- Consider reading a file from disk for a process:
  - Determine device holding file
  - Translate name to device representation
  - Physically read data from disk into buffer
  - Make data available to requesting process
  - Return control to process





## Life Cycle of An I/O Request






### **STREAMS**

- STREAM a full-duplex communication channel between a userlevel process and a device in Unix System V and beyond
- A STREAM consists of:
  - STREAM head interfaces with the user process
  - driver end interfaces with the device
  - zero or more STREAM modules between them
- Each module contains a read queue and a write queue
- Message passing is used to communicate between queues
  - Flow control option to indicate available or busy
- Asynchronous internally, synchronous where user process communicates with stream head





#### **The STREAMS Structure**







- I/O a major factor in system performance:
  - Demands CPU to execute device driver, kernel I/O code
  - Context switches due to interrupts
  - Data copying
  - Network traffic especially stressful





### **Intercomputer Communications**









- Reduce number of context switches
- Reduce data copying
- Reduce interrupts by using large transfers, smart controllers, polling
- Use DMA
- Use smarter hardware devices
- Balance CPU, memory, bus, and I/O performance for highest throughput
- Move user-mode processes / daemons to kernel threads








## I/O Performance of Storage (and Network Latency)







#### Homework

#### Exercises at the end of Chapter 12 (OS book)

• 12.5



# End of Chapter 12

